

Amlib Client Patch Installation Guide

Version 5.4.1

Last Updated: 8 October 2013

Only for customers who have previously upgraded their *Amlib Client* to Version 5.4

Amlib Client Patch Installation Guide

© 2013 OCLC (UK) Ltd

ALL RIGHTS RESERVED. Permission is granted to electronically copy and to print in hard copy portions of this document for training purposes by licensed users of the Amlib Library Management System. Any other uses – including reproduction for purposes other than those noted above, modification, distribution, republication, transmission, re-transmission, modification, or public showing – without the prior written permission of *OCLC (UK) Ltd* – is strictly prohibited.

Support:

Australia: 1300 260 795 (Local call cost in Australia)

Email:

support-amlib@oclc.org

Amlib Help Desk (TOPDesk):

<https://servicedesk.oclc.org/tas/public/>

OCLC Amlib Document Portal:

<https://www.oclc.org/support/services/amlib.en.html>

Sales:

Australia: 1300 260 795 (Local call cost in Australia)

Fax: +61 (0) 3 9929 0801

Email: sales-amlib@oclc.org

www.oclc.org/en-AU/

Amlib Client Patch Installation Guide

TABLE OF CONTENTS

WELCOME	4
OVERVIEW	4
BEFORE YOU BEGIN THE INSTALLATION.....	5
Read the Installation Notes First.....	5
Option to Install to Test Database First.....	5
Customised Report Templates	5
Serial Numbers NOT Required for Installation of Amlib Modules	5
Frequently Asked Questions	6
AMLIB Supported Operating Systems & System Requirements	9
Database Server	9
NetOpacs (Web Opac) Application Web Server.....	9
PC Client (for Client Server Modules including Offline)	9
SECTION 1: UPGRADE AMLIB SERVER AND DATABASE.....	10
Step 1: Log All Users out of Amlib	10
Step 2: Install the Amlib Client 5.4.1 Patch	10
Step 3: Run the Amlib 5.4 Changes Extra Script using the Amlib Upgrade Utility	14
SECTION 2: UPDATE ALL PCS	18
Step 1: Install the Amlib Client 5.4.1 Patch	18
SECTION 3: UPGRADE NETOPACS & ASSOCIATED PRODUCTS.....	18
SECTION 4: ADVISE OCLC (UK) LTD OF COMPLETION	18
APPENDICES	19
Appendix A: Silent Mode Command Line Parameters	19

Amlib Client Patch Installation Guide

WELCOME

Welcome to the *Amlib 5.4.1 Client Patch* Installation Guide.

This is a patch release containing updated modules and new reports. The complete installation time is estimated at less than one (1) hour to complete.

Please Note: This document has been prepared for all libraries that currently have *Amlib Client 5.4* installed. For users who haven't previously upgraded from 5.4 please contact Amlib Support for information on upgrading.

OVERVIEW

The upgrade of the *Amlib* client involves the following steps:

1. Upgrade of the *Amlib* client application to *Amlib Client 5.4.1*
2. The execution of the *Amlib 5.4 Changes Extra Script* to reconfigure the *Amlib* SQL databases using **Upgrade.exe**

IMPORTANT: Please check your version of Amlib **before** running the patch. It is very important that you only run this patch if you are currently running Amlib Version 5.4. To check your current version of Amlib:

1. In *Amlib* navigate to **Main > Base > About Release**
2. Note the version number at the top of the screen

Amlib Client Patch Installation Guide

BEFORE YOU BEGIN THE INSTALLATION...

Read the Installation Notes First

Please carefully read the entire installation guide prior to commencing the actual *Amlib* release update.

If you have any questions please contact: support-amlib@oclc.org.

Follow the instructions precisely and do not run any scripts against the database more than once. If you have any difficulties, please call *OCLC (UK) Ltd* immediately.

Option to Install to Test Database First

If you would like to only install this release in your test *Amlib* database, please email support-amlib@oclc.org before proceeding.

Customised Report Templates

WARNING!

Sites that have *customised* any report templates MUST ensure that the customised templates have been saved with a new name (with backup copies saved elsewhere).

- The report templates are located in the **Reports** folder on your *Amlib* server – for example:
C:/Amlib/Reports

If you have not renamed your templates after making changes, they will be *overwritten* during the upgrade as the incoming template file names will match on the existing template file names.

As part of the upgrade process, all current report templates will be saved into the *Amlib/Previous/Reports* folder.

Serial Numbers NOT Required for Installation of Amlib Modules

- The *Amlib Client 5.4.1 Patch* DOES NOT require a serial number

Amlib Client Patch Installation Guide

Frequently Asked Questions

Question: How much space do I need to have on my server?

- This will vary from library to library, depending on the number of bibliographic records held in the database. Generally libraries should ensure they have at least 5 Gb free space on their database server

Question: Do I need to have a completed backup of my system before proceeding?


- Yes. *OCLC (UK) Ltd* recommends that the library verify that it has an up-to-date backup of its database (for example: from the previous night) before installing any updates. You should also make sure that your tape backup includes a backup of your *Amlib* client folder (for example: **C:\Amlib**).
- Also if you have customised any report templates, please ensure they have been renamed and a copy saved elsewhere. If you have not renamed your templates after making changes, they will be overwritten by the upgrade as the incoming file name will match on the existing file name.

Question: Do I need to update each PC with the *Amlib Client Patch*?

- In addition to the database server itself, the *Amlib Client 5.4.1 Patch* needs to be installed on each PC that has the *Amlib* software loaded on the local hard disk


Question: How do I know whether *Amlib* is loaded from my local PC?

- Right-click on the *Amlib* icon on your desktop and select **Properties** – the Amlib Toolbar Properties window will display
- The Target field will show you where your *Amlib* client is installed:
 - a. If it has something like **C:\Amlib** (or **D:\Amlib**, **E:\Amlib** depending on the hard drives in your computer) then it is installed locally



- b. If it starts with two back slashes (\\) and then a name or IP address, it is installed on a server:

Amlib Client Patch Installation Guide



- If you are having trouble identifying where *Amlib* is installed please contact your IT Department or **Amlib Support** for assistance

Amlib Client Patch Installation Guide

Question: Do all users need to be logged out of *Amlib*?

- Yes. All users should be completely logged out from all *Amlib* client modules when installing the new *Amlib* client release UNTIL the entire upgrade processes are completed
- Libraries using the *NetOpacs* module should ensure that this program is also shutdown

Question: Can OCLC (UK) Ltd install the patch for me?

- Yes. *OCLC (UK) Ltd* can arrange for the onsite installation of this upgrade for a fee

Amlib Client Patch Installation Guide

AMLIB SUPPORTED OPERATING SYSTEMS & SYSTEM REQUIREMENTS

Database Server

Operating System	<ul style="list-style-type: none">• <i>Windows 2000, 2003, 2008</i>• <i>Linux (and Unix)</i>
RDBMS	<ul style="list-style-type: none">• <i>Microsoft SQL Server 2000, 2005, 2008 R2</i>• <i>Oracle 9i, 10g, 11gR2</i>
Memory (RAM)	<ul style="list-style-type: none">• Depends on operating system, volume & RDBMS selected.• Minimum 2GB RAM for SQL Server• Minimum 2GB RAM for Oracle
Hard Disk	<ul style="list-style-type: none">• Depends on volume. Using multiple Fast SCSI-3 Disk Drives (for example: more SCSI drives provides better performance)
Backup	<ul style="list-style-type: none">• Removable backup device (for example: 4mm DAT Tape Drive)

NetOpacs (Web Opac) Application Web Server

Operating System	<ul style="list-style-type: none">• <i>Windows 2000, 2003, 2008 with IIS pre-installed</i>
Memory (RAM)	<ul style="list-style-type: none">• Depends on operating system and volume• Minimum 2GB RAM for Windows 2003/2008

Although NetOpacs can operate on the same Amlib Database Server, it is recommended that medium to large libraries should implement a dedicated NetOpacs Server for maximum performance & security.

PC Client (for Client Server Modules including Offline)

Operating System	<ul style="list-style-type: none">• <i>Windows XP, 2000, Vista, Windows 7</i>
Memory (RAM)	<ul style="list-style-type: none">• Minimum 256 Mb for <i>Windows XP</i>• Minimum 256 Mb for <i>Windows 2000</i>• Minimum 1GB for <i>Windows 7</i>• Minimum 1GB for <i>Windows Vista</i>
Display	<ul style="list-style-type: none">• SVGA (800x600) minimum
Web Browser	<ul style="list-style-type: none">• <i>Internet Explorer 7</i> and above (will also work with other JAVA enabled browsers)

- **Important Note:** the above requirements are provided as a general guideline only

Amlib Client Patch Installation Guide

SECTION 1: UPGRADE AMLIB SERVER AND DATABASE

The *Amlib Client 5.4.1 Patch* needs to be installed on both the *Amlib* server and any PCs with the *Amlib* client installed locally.

Please Note: This process should take less than an hour depending on the size of your database and server configuration. (If you are reading this document for the first time and have not yet started the *Amlib Client 5.4.1 Patch*, you can copy your **Live** database to your **Test** database, and run the script on the **Test** database first to ascertain how long it will take).

Step 1: Log All Users out of Amlib

- Ensure all users have logged out of the *Amlib* client
- Libraries using *NetOpacs* will need to ensure that the *NetOpacs* program has been shutdown on the web server(s)
- *OCLC (UK) Limited* recommends that the library verify that it has an up-to-date **backup** of its database (for example: from the previous night) before installing any updates

Step 2: Install the Amlib Client 5.4.1 Patch

IMPORTANT: Please ensure that you have **full read/write** access to the **\Amlib** folder on your server (for example: **C:\Amlib**) and that you are logged in with Administrative Privileges.

1. The *Amlib Client 5.4.1 Patch* installer is available on the OCLC Website, under Updates and Patches>Amlib Client:
<https://www.oclc.org/support/services/amlib/downloads-software-updates/version5-4/updates-and-patches.en.html>


(contact *Amlib* support if you require a login to this website)

2. Download the **Amlib541Patch.exe** and save it on your *Amlib* server
3. Double-click the **Amlib541Patch.exe** to launch the installation Wizard – the Setup – Amlib Client screen will open displaying the **Welcome** message:

Amlib Client Patch Installation Guide




4. Click the **Next** button – the Installation Location screen will be displayed
5. Setup will search for the existing folder where the *Amlib* client is currently installed (if it is unable to find the existing folder a default folder will display)



6. If the folder displayed IS NOT correct then click the **Browse** button to manually locate the location of the existing **\Amlib** folder
7. Click the **Next** button – the Select Components screen will display:

Amlib Client Patch Installation Guide




8. Choose which components should be installed:

Modules To Install:


- **Amlib Staff User (Full)** – upgrades *Amlib* Staff Client (catalogue, circulation, etc.)

9. Select options and click the **Next** button – the Ready to Install screen will display with a summary of the installation tasks to be performed:



10. Click the **Install** button – the Installing screen will display:

Amlib Client Patch Installation Guide



11. When complete click the **Finish** button



12. The setup Wizard will close

Installation of the *Amlib Client 5.4.1 Patch* update is now complete.


Amlib Client Patch Installation Guide

Step 3: Run the Amlib 5.4 Changes Extra Script using the Amlib Upgrade Utility


After successfully installing the *Amlib Client 5.4.1* software on the server, you will need to run the **Upgrade.exe** utility to update your *Amlib* SQL databases with the new tables and columns for this patch.

WARNING! Do not run any of these Upgrade Scripts on the same database more than once. If you have any difficulties, please contact Amlib Support immediately.

1. To start the *Amlib Upgrade* utility, click on the Windows **Start** menu and select **Run** – the Run dialog window will display:




2. In the Open: field type in: **c:\amlib\upgrade** and click the **OK** button (replace **c:\amlib** with the correct path of your *Amlib Client* folder if different)
3. The Amlib Upgrade screen will display:




4. From the menu, select **File > Login...** - the Login dialog box will display:

Amlib Client Patch Installation Guide



5. Ensure the **Database authentication** option is selected
6. Enter the following:
 - a. Login name: **SYSADM**
 - b. Password: **SYSADM**
 - c. Select the Database: to update (default is the **Live** database)

Please Note: The login is case-sensitive. If typed in lowercase, it will appear as uppercase, but you **MUST** type it in uppercase.




7. Click the **OK** button


The Amlib Upgrade utility should now be logged into your SQL database.

8. From the menu, select **File > Open...** - the Open dialog box will display:


Amlib Client Patch Installation Guide



- In the **Scripts** subfolder (for example: **C:\Amlib\Scripts**), select the **Amlib 5.4 ChangesExtra.sql** file and click on the **Open** button
- A prompt will display with the following message: **This script will modify the database for use with the Amlib Patch Release Version 5.4.1. Do you wish to Continue?**



- Click the **Yes** button (select **No** if the SQL script has previously been run on this database and you have selected to run this script by mistake)
- The system will immediately start updating the database for the **Amlib 5.4.1** system changes
- On successful completion of the upgrade script a prompt will display with the following message: **The upgrade script for Amlib Patch Release Version 5.4.1 is complete. Please check the file "upgrade.log" for any errors.**



- Click the **OK** button

Amlib Client Patch Installation Guide

15. To exit the *Amlib Upgrade* utility, from the menu select **File > Exit**

The database has been successfully updated.

- To upgrade your sites **Test** database (available at most sites), Local History database (selected sites only) repeat the above **except** select the required database (for example: **Test**) **DO NOT select the Live database again!**

IMPORTANT NOTE: for customers with single shared AMCAT database with multiple AMLIB databases

You will need to re-run the **Amlib 5.4 ChangesExtra.sql** script at each library with a separate AMLIB database, even if they are using a shared AMCAT database that has already had the script applied.

Amlib Client Patch Installation Guide

SECTION 2: UPDATE ALL PCS

Step 1: Install the Amlib Client 5.4.1 Patch

Please ensure that you have full read/write access to the **\Amlib** folder (for example: **C:\Amlib**) and that you are logged in with Administrative Privileges.

- To install the *Amlib Client 5.4.1 Patch* to local machines, simply follow the instructions in **Section 1 – Step 2: Install the Amlib Client 5.4.1 Patch** above

PLEASE NOTE:

- If the *Amlib Client* software is installed on each PC: EVERY PC that has the *Amlib Client* software installed on it will need to have the above *Amlib Client 5.4.1 Patch* loaded on the local hard drive (for example: **C:\Amlib**)
- If separate *Amlib OPAC Client* software is installed separately on an OPAC terminal: the *Amlib Client 5.4.1 Patch* above will also need to be installed to the folder containing the *Amlib OPAC Client* software (**EXCEPT** only choose the option **Amlib Opac Only** at instruction 5)
- Refer to [Appendix A](#) (at the end of this document) for optional information of **Silent Mode Command Line Parameters** available for installing the *Amlib* client

SECTION 3: UPGRADE NETOPACS & ASSOCIATED PRODUCTS

After the upgrade of the *Amlib* client to *Version 5.4.1*, sites will then need to upgrade their *NetOpacs* (where applicable).

- See separate guide for installation details

SECTION 4: ADVISE OCLC (UK) LTD OF COMPLETION

To enable *OCLC (UK) Ltd* to verify that the Upgrade has been installed correctly please e-mail the **upgrade.log** to:

- support-amlib@oclc.org

This file will be located in the **\Amlib\Scripts** folder on the PC/server.

Amlib Client Patch Installation Guide

APPENDICES

Appendix A: Silent Mode Command Line Parameters

The *Amlib Client 5.4.1 Patch* installer features the option to install with silent mode command parameters - ideal if you wish to automatically distribute to *Amlib* Staff Workstations as part of a login script.

For example:

- **Amlib533Patch.exe /VERYSILENT /SUPPRESSMSGBOXES /NOCANCEL /DIR="c:\amlib"**

(Installs the *Amlib Client 5.4.1 Patch* silently to the **C:\Amlib** on the workstation)

Details of available parameters are:

/SILENT, /VERYSILENT

Instructs Setup to be silent or very silent. When Setup is silent the wizard and the background window are not displayed but the installation progress window is. When a setup is very silent this installation progress window is not displayed. Everything else is normal so for example error messages during installation are displayed unless disabled using **/SUPPRESSMSGBOXES**

If a restart is necessary and the **'/NORESTART'** command isn't used (see below) and Setup is silent, it will display a **Reboot now?** message box. If it's very silent it will reboot without asking.

/SUPPRESSMSGBOXES

Instructs Setup to suppress message boxes. Only has an effect when combined with **'/SILENT'** and **'/VERYSILENT'**.

The default response in situations where there's a choice is:

- Yes in a 'Keep newer file?' situation.
- No in a 'File exists, confirm overwrite.' situation.
- Abort in Abort/Retry situations.
- Cancel in Retry/Cancel situations. -
- Yes (=continue) in a DiskSpaceWarning/DirExists/DirDoesntExist/NoUninstallWarning/ExitSetupMessage/ConfirmUninstall

situation.

- Yes (=restart) in a FinishedRestartMessage/UninstalledAndNeedsRestart situation.

5 message boxes are not suppressible:

- The About Setup message box.
- The Exit Setup? message box.
- The FileNotInDir2 message box displayed when Setup requires a new disk to be inserted and the disk was not found.
- Any (error) message box displayed before Setup (or Uninstall) could read the command line parameters.
- Any message box displayed by [Code] support function MsgBox.

/NOCANCEL

Prevents the user from cancelling during the installation process, by disabling the Cancel button and ignoring clicks on the close button. Useful along with **'/SILENT'** or **'/VERYSILENT'**.

/NORESTART

Instructs Setup not to reboot even if it's necessary.

/RESTARTEXITCODE=exit code

Specifies the custom exit code that Setup is to return when a restart is needed. Useful along with **'/NORESTART'**. Also see Setup Exit Codes.

/DIR="x:\dirname"

Overrides the default directory name displayed on the Select Destination Location wizard page. A fully qualified pathname must be specified.

/PASSWORD=password

Specifies the Password (Serial Key) to use.

When an invalid password is specified, this command line parameter is also ignored.

Amlib Client Patch Installation Guide

/GROUP="folder name"

Overrides the default folder name displayed on the Select Start Menu Folder wizard page.

/NOICONS

Instructs Setup to initially check the Don't create any icons check box on the Select Start Menu Folder wizard page.

/COMPONENTS="comma separated list of component names"

Overrides the default components settings. Using this command line parameter causes Setup to automatically select a custom type.

(You will need to contact Amlib Support for a complete list of Components that are available to choose from, depending on which Installer is being used)

/TASKS="comma separated list of task names"

Specifies a list of tasks that should be initially selected or deselected. To deselect a task, prefix its name with a "!" character.

Only the specified tasks (and their children) will be selected; the rest will be deselected. Use the /MERGETASKS parameter instead if you want to keep the default set of tasks and only select/deselect some of them.

Examples:

Deselect all tasks, then select the "desktopicon" and "fileassoc" tasks:

```
/TASKS="desktopicon,fileassoc"
```

Deselect all tasks, then select a parent task item, but exclude one of its children:

```
/TASKS="parent,!parent\child"
```

/MERGETASKS="comma separated list of task names"

Like the /TASKS parameter, except the specified tasks will be merged with the set of tasks that would have otherwise been selected by default.

If UsePreviousTasks is set to yes, the specified tasks will be selected/deselected after any previous tasks are restored.

Examples:

Keep the default set of selected tasks, but additionally select the "desktopicon" and "fileassoc" tasks:

```
/MERGETASKS="desktopicon,fileassoc"
```

Keep the default set of selected tasks, but deselect the "desktopicon" task:

```
/MERGETASKS="!desktopicon"
```

/LOG

Causes Setup to create a log file in the user's TEMP directory detailing file installation and [Run] actions taken during the installation process. This can be a helpful debugging aid. For example, if you suspect a file isn't being replaced when you believe it should be (or vice versa), the log file will tell you if the file was really skipped, and why.

The log file is created with a unique name based on the current date. (It will not overwrite or append to existing files.)

The information contained in the log file is technical in nature and therefore not intended to be understandable by end users. Nor is it designed to be machine-parseable; the format of the file is subject to change without notice.

/LOG="filename"

Same as /LOG, except it allows you to specify a fixed path/filename to use for the log file. If a file with the specified name already exists it will be overwritten. If the file cannot be created, Setup will abort with an error message.

/LOADINF="filename"

Instructs Setup to load the settings from the specified file after having checked the command line. This file can be prepared using the '/SAVEINF=' command as explained below.

Don't forget to use quotes if the filename contains spaces.

/SAVEINF="filename"

Instructs Setup to save installation settings to the specified file.

Don't forget to use quotes if the filename contains spaces.